
## **Fixing You Tube Flickering**

Open Google Chrome

Click three dots in the top right corner and select settings



On settings screen, scroll to bottom and click Advanced

🗘 Settings X +				
← → C  G Chrome   chrome://settings ≡ Settings	Q. Search settings			
	Customize fonts		•	
	Page zoom	100%	•	
	Search engine			
	Search engine used in the address bar	Google		
	Manage search engines		+	
	Default browser			
	Google Chrome is your default browser			
	On startup			
	O Open the New Tab page			
	O Continue where you left off			
	<ul> <li>Open a specific page or set of pages</li> </ul>			
	Wilkes-Barre Area School District http://www.wbasd.k12.pa.us/		:	
	Add a new page			
	Use current pages			
	Advanced			
	Autaineu			

Settings x +		
← → C  G Chrome   chrome//settings ≡ Settings	Q Search settings	
	Location C:\Users\gmanning\Downloads	Change
	Ask where to save each file before downloading	
	Open certain file types automatically after downloading	Clear
	Printing	
	Printers	•
	Google Cloud Print	•
	Accessibility	
	Add accessibility features Open Chrome Web Store	
	System	
	Continue running background apps when Google Chrome is closed	
	Use hardware acceleration when available	
	Open proxy settings	
	Reset and clean up	
	Restore settings to their original defaults	•
	Clean up computer	•

Scroll down to System Section (Towards bottom of screen)

## Turn off Use hardware acceleration when available. Then click Relauch

settings x +     t     ← → C      G Chrome   chrome://settings				- 0 \$	
E Settings	Q. Search settings			A	Č
	Location C:Usersigmanning:Downloads Ask where to save each file before downloading Open certain file types automatically after downloading	Change			Î
	Printing				
	Printers	•			
	Google Cloud Print	•			
	Accessibility				
	Add accessibility features Open Chrome Web Store	Z			
	System				
	Continue running background apps when Google Chrome is closed	-	Turn off		
	Use hardware acceleration when available	Relaunch	Turn off		
	Open proxy settings				1
	Reset and clean up				
	Restore settings to their original defaults	· ·			
	Clean up computer	•			

That is it, videos should work fine now.